

## **General Disclaimer**

### **One or more of the Following Statements may affect this Document**

- This document has been reproduced from the best copy furnished by the organizational source. It is being released in the interest of making available as much information as possible.
- This document may contain data, which exceeds the sheet parameters. It was furnished in this condition by the organizational source and is the best copy available.
- This document may contain tone-on-tone or color graphs, charts and/or pictures, which have been reproduced in black and white.
- This document is paginated as submitted by the original source.
- Portions of this document are not fully legible due to the historical nature of some of the material. However, it is the best reproduction available from the original submission.

E83-10401

CR-171 688

# AgRISTARS

"Made available under NASA sponsorship  
in the interest of early and wide dis-  
semination of Earth Resources Survey  
Program information and without liability  
for any use made thereof."

A Joint Program for  
Agriculture and  
Resources Inventory  
Surveys Through  
Aerospace  
Remote Sensing


## Supporting Research

June 1983

### DATA MANAGEMENT PROCEDURES FOR TIEPOINT REGISTRATION, PRE- AND POST-PROCESSING, AND 'ICD116'

B. S. Nowakowski



 **Lockheed Engineering and Management  
Services Company, Inc.**



N83-34394

(E83-10401) DATA MANAGEMENT PROCEDURES FOR  
TIEPOINT REGISTRATION, PRE AND POST  
PROCESSING, AND ICD116 (Lockheed Engineering  
and Management) 48 p HC A03/MF A01 CSCL 05B

Unclas  
G3/43 00401



Lyndon B. Johnson Space Center  
Houston, Texas 77058

1. Report No. JSC-18886; SR-L3-04430		2. Government Accession No.		3. Recipient's Catalog No.	
4. Title and Subtitle  DATA MANAGEMENT PROCEDURES FOR TIEPOINT REGISTRATION, PRE AND POST PROCESSING, AND 'ICD116'				5. Report Date June 1983	
				6. Performing Organization Code 26-43	
7. Author(s) B. S. Nowakowski				8. Performing Organization Report No. LEMSCO-19428	
				10. Work Unit No. J.O. 71-622	
9. Performing Organization Name and Address  Lockheed Engineering and Management Services Company, Inc. 1830 NASA Road 1 Houston, Texas 77258				11. Contract or Grant No. NAS 9-15800	
				13. Type of Report and Period Covered Procedures	
12. Sponsoring Agency Name and Address  National Aeronautics and Space Administration Lyndon B. Johnson Space Center Houston, Texas 77058				14. Sponsoring Agency Code SC6	
15. Supplementary Notes					
16. Abstract  The title of the document is "Data Management Procedures for Tiepoint Registration, Pre and Post Processing, and 'ICD116'." The contents include two main sections: Section 1 is the procedures. With each procedure description, the pertinent execs are listed and purposes defined. The second section contains an example run of each of the 32 execs with user inputs identified. Additions and corrections will be incorporated in the master copy as required.  The Data Processing Section will maintain current execs on their account; however, most of the software is uncontrolled, not acceptance tested and can be changed without notice. These procedures were written for and reside in the Data Processing Section of the Scientific Systems Department.  <div style="text-align: center;">ORIGINAL PAGE IS OF POOR QUALITY</div>					
17. Key Words (Suggested by Author(s))  Tiepoint Registration ICD116 Execs			18. Distribution Statement  JSC Library CASPAN Library B. S. Nowakowski (5)		
19. Security Classif. (of this report)  None	20. Security Classif. (of this page)  None		21. No. of Pages  47	22. Price*	

\*For sale by the National Technical Information Service, Springfield, Virginia 22161

ORIGINAL PAGE IS  
OF POOR QUALITY

DATA MANAGEMENT PROCEDURES  
FOR TIEPOINT REGISTRATION, PRE AND POST PROCESSING, AND 'ICD116'

JOB ORDER 71-622

PREPARED BY

B. S. Nowakowski  
B. S. Nowakowski

APPROVED BY

A. J. Bowen, Jr.  
A. J. Bowen, Jr., Supervisor  
Data Processing Section

R. K. Lenington  
R. K. Lenington, Manager  
Scientific Systems Department

Prepared by

Lockheed Engineering and Management Services Company, Inc.

for

Information Science Branch

National Aeronautics and Space Administration  
Lyndon B. Johnson Space Center  
Houston, Texas

June 1983

# CONTENTS

ORIGINAL PAGE IS  
OF POOR QUALITY

Section	Page
1. THE PROCEDURES.....	1
1.1 IMAGE PREPROCESSING.....	1
1.2 THE 'ICD116' PROCEDURE (INTERFACE TO ERSYS REGISTRATION)....	3
1.3 THE GILBERT/VICAR TIEPOINT REGISTRATION PROCEDURE.....	4
1.4 IMAGE POST-PROCESSING.....	7
2. DOCUMENTED 'EXEC'S' USED IN ABOVE PROCEDURES (IN ALPHABETICAL ORDER).....	8

	<u>Page</u>
CONVERT EXEC.....	9
DSIZE EXEC.....	10
EXPAND2 EXEC.....	11
FLICKER IASCMD (IAS).....	12
GILBEAR EXEC.....	13
GRABIAS EXEC.....	14
HOCUTT EXEC.....	15
ICD116D EXEC.....	16
ICD116M EXEC.....	18
ICD116T EXEC.....	20
JIMBOB EXEC.....	21
LAS2IAS1 EXEC.....	22
LOOP TIE EXEC.....	23
MEANTIME EXEC.....	26
RPCHK EXEC.....	27
SAR EXEC.....	28
SARLAS EXEC.....	29
SARLASA EXEC.....	30
SETUP EXEC.....	31
SETUP IASCMD (IAS).....	31
SIZE EXEC.....	32
TAPCHK EXEC.....	33
TAPCON.....	34
TAPSCAN EXEC.....	35
TIEPOINT EXEC.....	36
TIEREG4 EXEC.....	37
TIEREG5 EXEC.....	38
TIEREG5B EXEC.....	39
TRIBIG EXEC.....	40
TRI REG EXEC.....	41
URITE2 EXEC.....	42
WRTAPE EXEC.....	45

## 1. THE PROCEDURES

### 1.1 IMAGE PREPROCESSING

The Gilbert/Vicar tiepoint registration will process any type or size of image data, but preprocessing is necessary to aid the user and make the process more manageable. The images must be in band sequential format. The following execs include most extracts and image preprocessing that will be required. If these are not adequate, please contact J. Gilbert for further help.

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
CONVERT EXEC	Converts various formats from BIL to BSQ.	p. 9
JIMBOB EXEC	Outputs TM SCROUNGE tape header information.	p. 21
RPCHK EXEC	Defines primary and secondary path/row and outputs beta angle in degrees and radians.	p. 27
MEANTIME EXEC	Outputs the approximate starting line and starting sample of an area of interest from a TM SCROUNGE tape.	p. 26
SARLAS EXEC	Extracts an area of interest from a TM SCROUNGE 'P' tape.	p. 29
SARLASA EXEC	Extracts an area of interest from a TM 'A' tape.	p. 30
SAR EXEC	Extracts an area within an extract.	p. 28
SIZE EXEC	Scales the image to a different size.	p. 32

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
DSIZE EXEC	Scales the image to a smaller size.	p. 10
LAS2IAS1	Averages every 14 lines and 14 pixels of TM SCROUNGE full frame.	p. 22

## 1.2 THE ICD116 PROCEDURE

If ERSYS registration is to be used, the images may be preprocessed using the appropriate execs in Section 1.1. ERSYS registration is more accurate than the tiepoint registration method, but is less flexible and requires more knowledge about the data. Input images should be BSQ and no larger than 1144 lines and 1144 pixels.

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
ICD116D EXEC	Prepares data for interface tape to registration using TM image data.	p. 16
ICD116M EXEC	Prepares data for interface tape to registration using the EROS formatted band sequential data.	p. 18
ICD116T EXEC	Writes the ICD116 output to tape.	p. 20
TAPSCAN EXEC	Checks for physical read errors and reports record sizes.	p. 35

### 1.3 THE GILBERT/VICAR TIEPOINT PROCEDURES

#### 1.3.1

Display on the IAS, the reference image on screen 1 and the registrant on screen 2. (Please refer to IAS BASICS FOR THE NEW USER for display instruction.)

NOTE: If using MSS as reference and TM as registrant, the following exec will be useful.

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
SETUP EXEC (CMS)	Prepares setup IASCMD with proper arguments.	p. 31
SETUP IASCMD (IAS)	Displays MSS on screen 1 and TM image on screen 2.	p. 31

#### 1.3.2

Choose and list tiepoint coordinates. This step requires patience and accuracy because the output registered image will be only as good as your tiepoints. The number of tiepoints depends on the particular registration program being used.

##### 1.3.2.1

Using cursor form 0, place the cursor on a point in the reference; read and record the virtual image coordinates. (Please refer to IAS BASICS FOR THE NEW USER for cursor instruction.)

### 1.3.2.2

Now, place the cursor on the same point on the registrant; read and record the virtual image coordinates.

### 1.3.3

Execute the TIEPOINT EXEC - make sure all entries are correct; one mistake will destroy accuracy.

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
TIEPOINT EXEC	Converts IAS coordinates to coordinates used by the tiepoint programs.	p. 36

### 1.3.4

Execute the appropriate tiepoint program.

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
TIEREG4 EXEC	'exact fit' - requires very accurate tiepoints.	p. 37
TIEREG5 EXEC	'least squares fit' - averages errors globally.	p. 38
TIEREG5B EXEC	For TM images larger than 512L x 512P.	p. 39
TRIREG EXEC	For TM simulated data-uses triangulation.	p. 41
TRIBIG EXEC	For TM simulated images larger than 512L x 512P.	p. 40
LOOPTIE EXEC	Uses TIEREG5 and will register multiple bands with one set of inputs.	p. 23

### 1.3.5

Check registration quality - this should be done at various times to ensure quality and accuracy of the data and to save the user time.

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
FLICKER IASCMD	To 'blink' reference against registrant.	p. 12
IAS CURSOR	To measure one tiepoint against another.	IAS BASICS FOR THE NEW USER
IAS DISPLAY	To compare different images and band-to-band registration.	

#### 1.4 IMAGE POST-PROCESSING

The following steps are used by data management to ensure user uniformity and versatility. Registration output images will be written to tape in BIL format with a header and gains and biases applied. This output tape will be FR80 and RT&E data base compatible. These execs should be completed in order.

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
URITE2 EXEC	Converts the images to BIL format.	p. 42
EXPAND2 EXEC	Adds a header and gains and biases.	p. 11
WRTAPE EXEC	Writes the above to tape.	p. 45
TAPCHK EXEC	Outputs selective parts of the tape for checking the accuracy and validity of tape.	p. 33

At this point, the entire tape should be converted and checked on the IAS to make sure image data on the tape is correct. The following exec is helpful for converting an entire tape to IAS format.

<u>Name</u>	<u>Purpose</u>	<u>Example</u>
TAPCON	Converts 1 or more files from tape to IAS format.	p. 34

## 2. DOCUMENTED 'EXECs' USED IN THE PROCEDURES (in alphabetical order)

The user of the following 'execs' is assumed to be familiar with CMS and the IAS, and is using the SCREEN account. The documentation provided is an example of the 'EXEC' run with arrows indicating user response. These execs will in turn execute the appropriate programs. The majority will require that the user be linked to Jimmy Gilbert's T and U library disks. A few require Bill Hocutt's disk, or the IAS disk. Some 'execs' reside only on the SCREEN account. Below the typed name of each exec is the exec name which will link to the appropriate disks.

CONVERT EXEC  
(GRABIAS)

→ If tape is to be converted, mount on TAP1.

→ cconvert  
\*\*\* IAS Format Conversion Program \*\*\*

Enter One Of The Following Codes  
For The Input Format

U - Universal Format  
A - USCA Format  
L - LIVES Format  
V - VICAR Format  
E - EROS Format  
P - PFC Format  
Q - Band Sequential Format  
R - Registration Output Format  
N - None (No Formal Format)  
W - Universal Format (Production Version - Header Gain and Bias Applied)  
Z - Lives Format (Production Version - Header Gain and Bias Applied)  
S - Enter CMS Subset  
X - Exit this program

→ Enter Input Medium ... Disk or Tape ( D/T )

→ Enter FN FT FM for Data Set Number 1

→ i4985 81338 a  
EXECUTION BEGINS...

→ \*\*\* Enter The Number Of Channels (Default=4) \*\*\*

→ \*\*\* Enter The Starting Line Of The Image (Default=1) \*\*\*

→ \*\*\* Enter The Starting Sample (Default=1) \*\*\*

→ \*\*\* Enter The Number Of Lines Of The Image To Output (Default=All) \*\*\*

→ \*\*\* Enter The Number Of Samples Per Channel To Output (Default=All) \*\*\*

→ Enter blank for default output filename (CHANNEL1, CHANNEL2, ....)  
Output filename for channel 1 !!

→ e31  
FILEDEF 20 DISK E31 IASIMAGE \* (RECFM F LRECL 392 ELKSIZE 392  
Output filename for channel 2 !!

→ e32  
FILEDEF 21 DISK E32 IASIMAGE \* (RECFM F LRECL 392 ELKSIZE 392  
Output filename for channel 3 !!

→ e33  
FILEDEF 22 DISK E33 IASIMAGE \* (RECFM F LRECL 392 ELKSIZE 392  
Output filename for channel 4 !!

→ e34  
FILEDEF 23 DISK E34 IASIMAGE \* (RECFM F LRECL 392 ELKSIZE 392  
\*\*\* IAS Format Conversion Program \*\*\*

Enter One Of The Following Codes  
For The Input Format

U - Universal Format  
A - USDA Format  
L - LIVES Format  
V - VICAR Format  
E - EROS Format  
P - PFC Format  
Q - Band Sequential Format  
R - Registration Output Format  
N - None (No Formal Format)  
W - Universal Format (Production Version - Header Gain and Bias Applied)  
Z - Lives Format (Production Version - Header Gain and Bias Applied)  
S - Enter CMS Subset  
X - Exit this program

→ x  
R: T=4.32/8.56 07:24:42

ORIGINAL PAGE 15  
OF POOR QUALITY

DSIZE EXEC  
(GILBEAR)

```
→ dsize
Enter The FN, FT and FM of The File to Be Down Sized
→ boreal chan1 a
*** Enter The File Mode Of The Output Data Set ... ( Default = A ) ***
→ EXECUTION BEGINS...
*** ENTER THE NUMBER OF LINES IN THE AVERAGING (LINC) ***
→ 2
*** ENTER THE NUMBER OF SAMPLES IN THE AVERAGING (SINC) ***
→ 2
**BLIP**
**BLIP**
*** PROCESSING COMPLETE ***
FILENAME FILETYPE FM FORMAT LRECL RECS BLCKS DATE TIME
BOREAL ACHAN1 A1 V 316 316 99 6/09/83 8:20:56
R;
```

ORIGINAL PAGE IS  
OF POOR QUALITY

EXPAND2 EXEC  
(GILBEAR)  
(HOCUTT)

→ expand2 9656 82234u  
THIS PROGRAM IS DESIGNED TO READ UP TO 100 IMAGES FROM THE INPUT  
TAPE, CALCULATE BIAS AND GAIN VALUES FOR EACH FILE, AND TO COPY  
THE IMAGES FROM THE INPUT TO THE OUTPUT TAPE WHILE INSERTING  
THE BIAS AND GAIN VALUES IN THE HEADER OF EACH RECORD.  
AN OPTION HAS BEEN ADDED TO PERMIT DISK TO DISK PROCESSING OF A  
SINGLE FILE. THE INPUT FILE IS WRITTEN TO OUTPUT A AND THE OUTPUT FILE  
IS TM TEMP T. THESE FILE NAMES ARE SET IN THE EXEC AND MAY BE CHANGED.  
THE BIAS AND GAIN VALUES ARE ALSO APPLIED TO ALL PIXEL VALUES.  
INDICATE THE SIZE OF THE IMAGES ON THE INPUT TAPE.

1:	196	X	117	X	7
2:	386	X	308	X	7
3:	196	X	117	X	4
4:	497	X	426	X	3
5:	497	X	426	X	4
6:	386	X	308	X	4
7:	512	X	580	X	4
8:	392	X	324	X	4
9:	392	X	324	X	3
10:	196	X	182	X	3
11:	392	X	351	X	7
12:	392	X	324	X	7
13:	392	X	324	X	6

→ 12  
FILEDEF 10 DISK 9658 82234U A ( BLOCK 3060 RECFM U PERM  
FILEDEF 8 DISK TM9658 82234U A ( BLOCK 3060 RECFM U PERM  
FILEDEF 6 DISK EXPAND OUT A ( LRECL 132 BLKSIZE 132 RECFM F PERM  
EXEC CLRSCRN  
LOAD GBL12 EXPAND2 BSCAL1 TCDAY  
START  
EXECUTION BEGINS...  
\*\*\* ENTER A 1 FOR DISK INPUT OR A 2 FOR TAPE INPUT\*\*\*

→ 1  
PROCESSING FILE 1  
SUBROUTINE PSREAD  
SUBROUTINE TAPERF  
COPYING FILE NO 1  
ENTER JOB ID (TASK TITLE)  
--30 CHAR MAX--  
→ tm scroungeunregistered  
ENTER RUN ID (FILE TITLE)  
--14 CHAR MAX--  
→ chan c missreg

-----  
EXTRACTION COMPLETE  
-----

PPRINT EXPAND OUT A  
R:

ORIGINAL QUALITY  
OF EACH QUALITY

→ HIT TRACKBALL BUTTON 1 TO STOP FLICKER

GILBEAR EXEC

ORIGINAL PAGE 15  
OF POOR QUALITY

→ GILBEAR  
GETDISK TEMP MAXIMUM CLEAR B  
DMKLNK105E TEMP 151 NOT LINKED; R/W BY PR001  
DMKLNK105E TEMP 152 NOT LINKED; R/W BY JSC1645  
DMKLNK105E TEMP 153 NOT LINKED; R/W BY SRSG10  
TEMP 154 HAS BEEN ATTACHED AS 192.. (003000 KILCBYTES)  
192 HAS BEEN ACCESSED AS B DISK.  
LINK GILBEAR 191 499 RR  
DASD 499 LINKED R/O; R/W BY GILBEAR; R/O BY 003 USERS  
LINK GILBEAR 500 500 RR  
DASD 500 LINKED R/O; R/W BY GILBEAR; R/O BY 003 USERS  
ACC 499 T  
T (499) R/O  
ACC 500 U  
U (500) R/O  
R:

ORIGINAL PAGE IS  
OF POOR QUALITY

GRABIAS EXEC

—→ grabias  
IAS program disk attached as 'Q' disk.  
Send MAIL to IASMAINT with comments, suggestions, and problems  
TAPE 380 ATTACHED  
DEVICE 380 ATTACHED AS REQUESTED  
dealing with the Image Analysis Station.  
Enter 'HELP IAS NEWS' for latest IAS information.  
R;

ORIGINAL PAGE 15  
OF POOR QUALITY

HOCUTT EXEC

→ HOCUTT  
CP LINK JSC716 191 291 RR PASS= UGT  
DASD 291 LINKED R/O; R/W BY JSC716  
ACC 291 M  
M (291) R/O  
R:

ORIGINAL PAGE IS  
OF POOR QUALITY

ICD116D EXEC  
(GILBEAR)

The information needed for this exec can be obtained from the JIMBOB EXEC, SARLAS EXEC, RPCCHK EXEC, Jess Mansfield and Jim Boatright.

```

→ ICD116d
*** ENTER THE NUMBER OF CHANNELS TO FORMAT INTO ICD116 FORMAT ***
→ 7
*** ENTER THE FILE MODE OF THE OUTPUT ***
→ a
*** ENTER THE FILE NAME OF THE EXTRACT ED IMAGE DATA SET ***
→ tm8931
*** ENTER THE ( ALPHA MERIC ) FILE TYPE OF THE EXTRACT ED IMAGE **
→ 82246ex
*** ENTER THE FILE MODE OF THE EXTRACT ED IMAGE ***
→ a
GLOBAL TXTLIB PORTMOD2 CMSLIE WBLIE FTIO
FI 5 TERM
FI 6 TERM
FI 15 TERM
FI 16 TERM
FI 20 DISK ICD116 OUTPUT1 A { RECFM U BLOCK 360
FI 21 DISK ICD116 OUTPUT2 A { RECFM U BLOCK 3596
FI 22 DISK ICD116 OUTPUT3 A { RECFM U BLOCK 4048
FI 23 DISK ICD116 OUTPUT4 A { RECFM U BLOCK 3596
FI 31 DISK TM893L 82246EX1 A { RECFM U BLOCK 4000 PERM
FI 32 DISK TM893L 82246EX2 A { RECFM U BLOCK 4000 PERM
FI 33 DISK TM893L 82246EX3 A { RECFM U BLOCK 4000 PERM
FI 34 DISK TM893L 82246EX4 A { RECFM U BLOCK 4000 PERM
FI 35 DISK TM893L 82246EX5 A { RECFM U BLOCK 4000 PERM
FI 36 DISK TM893L 82246EX6 A { RECFM U BLOCK 4000 PERM
FI 37 DISK TM893L 82246EX7 A { RECFM U BLOCK 4000 PERM
FI 40 DISK CMS EXEC A { RECFM F BLOCK 80
LOAD ICD116D ( CLEAR START NOMAP
EXECUTION BEGINS...
THE TIME IS 8:45:56
THE DATE IS 3/15/83
*** ENTER THE EXTRACTION STARTING LINE ***
→ 1
*** ENTER THE EXTRACTION STARTING SAMPLE ***
→ 3416
*** ENTER WRS PATH ***
→ 027
*** ENTER WRS ROW ***
→ 031
*** Enter The Line Number Of The WRS Center ***
→ 1545.8
*** Enter The Sample Number Of The WRS Center ***
→ 1676.8
The Beta Angle Default Is 2.889986
Do You Wish To Change This Value (Y/N) ??
→ y
*** Enter The Beta Angle ***
→ 2.942608
*** ENTER THE SEGMENT NUMBER ***
→ 893
*** ENTER SEGMENT CENTER LAT DEGREES ***
→ 42
*** ENTER LAT MINUTES ***
→ 23
*** ENTER LAT SECONDS ***
→ 47
*** ENTER LAT N/S ***

```

ORIGINAL PAGE 15  
OF POOR QUALITY

```

→ n
*** ENTER THE SEGMENT CENTER LONG DEGREES ***
→ 94
*** ENTER LONG MINUTES ***
→ 10
*** ENTER LONG SECONDS ***
→ 29
*** ENTER LONG E/W ***
→ W
*** ENTER SUN ELEVATION ANGLE ***
→ 33
*** ENTER SUN AZIMUTH ***
→ 151
*** ENTER PATH-ROW NOMINAL LONG DEGREES ***
→ 94
*** ENTER LONG MINUTES ***
→ 32
*** ENTER LONG E/W ***
→ W
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
**BLIP**
*** LSSET IMAGE RECORD GENERATION CCMELETE ***
*** LSSET TRAILER RECORD GENERATION COMPLETE ***
FLIST ICD116 OUTPUT* A ( D
FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
ICD116 OUTPUT1 A1 V 360 1 3/15/83 8.46.28
ICD116 OUTPUT2 A1 V 3596 2 3/15/83 8.48.03
ICD116 OUTPUT3 A1 V 1192 8008 9338 3/15/83 8.56.58
ICD116 OUTPUT4 A1 V 3596 7 25 3/15/83 8.56.59
ERASE CMS EXEC A
R: -...

```

ICD116M EXEC  
(GILBEAR)

This exec uses EROS formatted band sequential data and writes a band interleave ICD116. This exec needs cleanup. Please contact Jimmy Gilbert when needed.

ORIGINAL PAGE IS  
OF POOR QUALITY

ICD116T EXEC  
(GILBEAR)

A scratch tape must be mounted on TAP1.

```
→ icd116t
  TAPE 181 ON TAPE 4C1
→ *** Enter The File Mode Of The ICD116 Data Sets ***
  a
  **BLIP**
  **BLIP**
  **BLIP**
  **BLIP**
  **BLIP**
  **BLIP**
  **BLIP**
  **BLIP**
  **BLIP**
  **BLIP**
  R;
→ tape wtm
  R;
→ tape wtm
  R;
```

PRECEDING PAGE BLANK NOT FILMED

JIMBOB EXEC  
(GILBEAR)

The first of the TM SCROUNGE 'P' tapes should be mounted.

```
GPHW 11000  
GPHW 181  
GLOBAL INDOOR COMPLETE  
FLEXIBLE EXTERIOR CABLE FORTMOD2 WIELIE FTIO  
PREFLECT 2  
CUT OFF  
FILM SPEED 60  
FILM 15  
FILM 15  
FILM 15  
LOAD TAP1 ( RECFB U BLOCK 99,9  
JIMBCB ( CLEAR NOMAP START  
EXECUTION BEGINS...  
WRS DESCRIPTION = D027031  
SCENE CENTER TIME = 82294162733080C  
WRS SCENE CENTER LAT/LONG = N N41-46/W094-29  
IMAGE FORMAT CENTER LAT/LONG = C H41-45/W094-28  
SUN ANGLES = SUN EL33 A151  
SCENE ID = -40097-16273-  
OFFERS 1412  
HPC CO  
HPC CO  
META = 521E154C
```

ORIGINAL PAGE IS  
OF POOR QUALITY

LAS2IAS1 EXEC  
(GILBEAR)

—→ Tape must be positioned at the beginning of the appropriate file.

—→ tape isf 4

—→ R: las2ias1

FI 5 TERM

FI 6 TERM

FI 15 TERM

FI 16 TERM

FI 10 TAB1 / RECFM FB BLOCK 28672 U I E C C K 7 1 6 8  
FI 11 DISK TM TASI IMAGE A Y RECFM U I E C C K 7 1 6 8

TAPE FSR 1

DESEUF

LCAD LAS2IAS / CLEAR NOMAP START

EXECUTION BEGINS...

\*\*\* THE SINC/LINC IS 14 \*\*\*

\*\*\* SENSED RECORD LENGHT IS 7168 \*\*\*

\*\*\* SENSED RECORD LENGHT IS 7168 \*\*\*

\*\*\* SENSED RECORD LENGHT IS 7168 \*\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*BLIP\*\*

\*\*\* Processing Complete \*\*\*

R:

LOOPTIE EXEC  
(GILBEAR)

→ LOOPTIE  
DESCRIBE  
EXEC TIER 335  
\*\*\* Enter the FN, FM and FT of the Image To Be Registered \*\*\*  
\*\*\* Enter the FN, FM and FT of the Registered Image Output \*\*\*  
\*\*\* Enter the FN, FM and FT of the Tiepoint Data Set \*\*\*  
EXECUTION BEGINS...  
\*\*\* TIEPOINT DATA... PROCESSED \*\*\*  
\*\*\* ENTER THE NUMBER OF LINES TO OUTPUT \*\*\*  
\*\*\* ENTER THE NUMBER OF SAMPLES TO OUTPUT \*\*\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
EXEC TIER 335  
\*\*\* Enter the FN, FM and FT of the Image To Be Registered \*\*\*  
\*\*\* Enter the FN, FM and FT of the Registered Image Output \*\*\*  
\*\*\* Enter the FN, FM and FT of the Tiepoint Data Set \*\*\*  
EXECUTION BEGINS...  
\*\*\* TIEPOINT DATA... PROCESSED \*\*\*  
\*\*\* ENTER THE NUMBER OF LINES TO OUTPUT \*\*\*  
\*\*\* ENTER THE NUMBER OF SAMPLES TO OUTPUT \*\*\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*\*\* PROCESSING COMPLETE \*\*\*  
FILE NAME: TIER 335 FM FORMAT RECS LKGS DATE TIME  
TIER 335 022402 A1 V 392 324 125 2/22/83 10.49.11  
DESCRIBE  
EXEC TIER 335  
\*\*\* Enter the FN, FM and FT of the Image To Be Registered \*\*\*  
\*\*\* Enter the FN, FM and FT of the Registered Image Output \*\*\*  
\*\*\* Enter the FN, FM and FT of the Tiepoint Data Set \*\*\*  
EXECUTION BEGINS...  
\*\*\* TIEPOINT DATA... PROCESSED \*\*\*  
\*\*\* ENTER THE NUMBER OF LINES TO OUTPUT \*\*\*  
\*\*\* ENTER THE NUMBER OF SAMPLES TO OUTPUT \*\*\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*  
\*BLIP\*

ORIGINAL PAGE IS  
OF POOR QUALITY

```

*** PROCESSING COMPLETE ***
FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
TMO886 12243 A1 V 392 324 125 2/22/83 10.54.24
EXEC TIEREG5
**** Enter The FN, FM And FT Of The Image To Be Regist ered ***
**** Enter The FN, FM And FT Of The Regist ered Image Out:ut ***
**** Enter The FN, FT And FM Of The Tiepoint Data Set ***
EXECUTION BEGINS...
*** TIEPOINT DATA PROCESSED ***
*** ENTER THE NUMBER OF LINES TO CUIPUT ***
*** ENTER THE NUMBER OF SAMPLES TO OUTPUT ***
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*** PROCESSING COMPLETE ***
FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
TMO886 82244 A1 V 392 324 125 2/22/83 11.00.14
DESEUF
EXEC TIEREG5
**** Enter The FN, FM And FT Of The Image To Be Regist ered ***
**** Enter The FN, FT And FM Of The Regist ered Image Out:ut ***
**** Enter The FN, FT And FM Of The Tiepoint Data Set ***
EXECUTION BEGINS...
*** TIEPOINT DATA PROCESSED ***
*** ENTER THE NUMBER OF LINES TO CUIPUT ***
*** ENTER THE NUMBER OF SAMPLES TO OUTPUT ***
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*** PROCESSING COMPLETE ***
FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
TMO886 82245 A1 V 392 324 125 2/22/83 11.03.37
DESEUF
EXEC TIEREG5
**** Enter The FN, FM And FT Of The Image To Be Regist ered ***
**** Enter The FN, FT And FM Of The Regist ered Image Out:ut ***
**** Enter The FN, FT And FM Of The Tiepoint Data Set ***
EXECUTION BEGINS...
*** TIEPOINT DATA PROCESSED ***
*** ENTER THE NUMBER OF LINES TO OUTPUT ***
*** ENTER THE NUMBER OF SAMPLES TO OUTPUT ***
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*

```

```

*CLIP*
*CLIP*
*CLIP*
*CLIP*
*** PROCESSING COMPLETE ***
FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
TM0386 822400 A1 V 392 324 125 2/22/83 11.09.03
DESCRT
EXEC TIEREG5
*** ENTER THE FM, FM AND FM OF THE Image To Be Regist ered ***
*** ENTER THE FM, FM AND FM OF THE Re,list ered Image Output ***
*** ENTER THE FM, FM AND FM OF THE Tiepoint Data Set ***
EXECUTION BEGINS..
*** TIEPOINT DATA PROCESSED ***
*** ENTER THE NUMBER OF LINES TO OUTPUT ***
*** ENTER THE NUMBER OF SAMPLES TO OUTPUT ***
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*** PROCESSING COMPLETE ***
FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
TM0386 822407 A1 V 392 324 125 2/22/83 11.15.04
SP CONS CLOSE STOP

```

The following is an example of the exec which must be edited for each run.  
The arrows indicate potential changes.

```

*****
* THIS EXEC TIEPOINT REGISTERS TM SCRUNGE DATA--ALL BANDS.
* INPUT EACH TIME, BEFORE RUNNING, THE FILENAME, FILETYPE, DATE
* OF ACQUISITION, AND THE NUMBER OF BANDS TO BE REGISTERED.
*****

```

```

SPOOL CONS CCVT START NOH CLASS E
&RAG = 1
-LOOP
->&FNI = SCCNCAT 82214EX &RAG
->&FNO = SCCNCAT 82214 &RAG
DISBUF
->&STACK LIFO 392
->&STACK LIFO 324
->&STACK LIFO TM0392A TIEPTS A
->&STACK LIFO TM0392 &FNO A
->&STACK LIFO TM0392 &FNI A
EXEC TIEREG5
GIF &FETCODE NE 0 SGOTO -ERR
&RAG = &RAG + 1
->&IF &RAG LE 4 SGOTC -LOOP
-ERR
SP CONS CLOSE STOP
EXEC RESET
EXIT

```

MEANTIME EXEC  
(GILBEAR)

→ Meantime  
EXECUTION BEGINS...  
→ \*\*\* Enter The Scene Center Latitude (Degrees) \*\*\*  
→ 41  
→ \*\*\* Enter The Scene Center Latitude (Minutes) \*\*\*  
→ 45  
  
→ \*\*\* Enter The Scene Center Longitude (Degrees) \*\*\*  
→ 94  
→ \*\*\* Enter The Scene Center Longitude (Minutes) \*\*\*  
→ 29  
  
→ \*\*\* Enter Latitude Direction ... 0 = North, 1 = South \*\*\*  
→ 0  
→ \*\*\* Enter Longitude Direction ... 0 = East, 1 = West \*\*\*  
→ 1  
Scene Center Latitude Is 41.748969  
Scene Center Longitude Is -94.468644  
→ ??? Are These Values Correct ... (0 = Yes, 1 = No) ???  
→ 0  
  
→ \*\*\* Enter The Number Of Lines To Extract \*\*\*  
→ 512  
→ \*\*\* Enter The Number Of Samples To Extract \*\*\*  
→ 512  
  
→ \*\*\* Enter The Extraction Center Latitude (Degrees) \*\*\*  
→ 42  
→ \*\*\* Enter The Extraction Center Latitude (Minutes) \*\*\*  
→ 24  
  
→ \*\*\* Enter The Extraction Center Longitude (Degrees) \*\*\*  
→ 94  
→ \*\*\* Enter The Extraction Center Longitude (Minutes) \*\*\*  
→ 10  
  
\*\*\* Computed Starting Line Is 56 \*\*\*  
\*\*\* Computed Starting Sample Is 3602 \*\*\*  
\*\*\* Enter The Number Of Lines To Extract \*\*\*

ORIGINAL PAGE IS  
OF POOR QUALITY

# RPCHK EXEC

→ RPCHK  
JSC735 191 HAS BEEN ATTACHED AS 243.  
G (243) R/O  
243 HAS BEEN ACCESSED AS G DISK.  
EXECUTION BEGINS...  
ENTER LAT AND LON TO CONVERT IN DEGREES MINUTES SEC (999 DEG TO EXIT)  
→ LAT = DDDD MM SS  
→ 0036 03 00  
→ LON = DDDD MM SS  
→ -390 37 00  
36.05 -90.62

INPUT LATITUDE = 36.05 INPUT LONGITUDE = -90.62  
LAT AND LON IN RADIANS = 0.62919104 -1.58155823  
ENTER NUMBER OF LINES & PIXELS  
XXXXX XXXXX

→ C5000 05000  
5000 5000  
ACI SIZE LINES= 5000 PIXELS= 5000

DAY	PATH	ROW
PRIMARY	23	35
SECONDARY	24	35
NIGHT	PATH	ROW
PRIMARY	121	209
SECONDARY	120	209

DAY	PATH	ROW
PRIMARY	23	35
SECONDARY	24	35
NIGHT	PATH	ROW
PRIMARY	121	209
SECONDARY	120	209

SCENE CENTERS	LATITUDE			LONGITUDE		
	DEG	MIN	SEC	DEG	MIN	SEC
PRIMARY DAY	36	3	0	-90	7	0
SECONDARY DAY	36	3	0	-91	40	0
PRIMARY NIGHT	36	3	0	-90	30	0
SECONDARY NIGHT	36	3	0	-89	18	0

SCENE ANGLES DEGREES	ORIENTATION	LEFT	RIGHT
PRIMARY DAY	10.1870174	3.1300000	13.1300000
SECONDARY DAY	10.1870174	3.1300000	13.1300000
PRIMARY NIGHT	10.1870174	-3.0900000	13.1300000
SECONDARY NIGHT	10.1870174	-3.0900000	13.1300000

CLEARANCES	TOP	BOTTOM	LEFT	RIGHT
PRIMARY DAY	-1175	-1425	-1251	-305
SECONDARY DAY	-1556	-1034	501	-2717
PRIMARY NIGHT	-1246	-1354	-746	-1410
SECONDARY NIGHT	-1632	-958	-3127	971

→ ENTER LAT AND LON TO CONVERT IN DEGREES MINUTES SEC (999 DEG TO EXIT)  
LAT = DDDD MM SS  
999

ORIGINAL PAGE IS  
OF POOR QUALITY

SAR EXEC  
(GILBEAR)

```

→ SAR
→ *** Enter The FN, FT And FM Of The Input Imagery ***
→ tm0886 022464
→ *** Enter The FN, FT And FM Of The Output Image ***
→ tm0886 022464
EXECUTION BEGINS...

→ nter The Starting Line
31

→ nter The Starting Sample
49

→ nter The Number Of Lines
324

→ nter The Number Of Samples
362
FILENAME FILETYPE FN FORMAT RECS BLKS DATE TIME
TM0886 022464 A1 V 392 324 123 2/22/83 3.48.47
R;

```

ORIGINAL PAGE IS  
OF POOR QUALITY.

SARLAS EXEC  
(GILBEAR)

→ sarlas

\*\*\* TM Extraction Program \*\*\*  
\*\*\* LASLIR Tape Input \*\*\*

→ \*\*\* Enter The Segment Number \*\*\*

893

→ \*\*\* Enter The Acquisition Date \*\*\*

32294

→ \*\*\* Enter The Tape Letter Designator \*\*\*

10

→ \*\*\* Enter The First Tape Numeric Value \*\*\*

8647

→ \*\*\* Enter The Starting Line Of The Extraction \*\*\*

56

→ \*\*\* Enter The Starting Sample Of The Extraction \*\*\*

3602

→ \*\*\* Enter The Number Of Lines To Output \*\*\*

512

→ \*\*\* Enter The Number Of Samples To Output \*\*\*

512

→ \*\*\* Enter The Band To Be Extracted, 0 For No More \*\*\*

1

10002 TAPE 108647 HAS BEEN REQUESTED ON UNIT 101 (TAPMOUNT)

10003 TAPE READY... EXECUTION CONTINUING (TAPMOUNT)

EXECUTION BEGINS...

→ \*\*\* Enter The Band To Be Extracted, 0 For No More \*\*\*

2

EXECUTION BEGINS...

→ \*\*\* Enter The Band To Be Extracted, 0 For No More \*\*\*

0

→ \*\*\* Extraction Run Completed \*\*\*

R;

ORIGINAL PAGE IS  
OF POOR QUALITY

SARLASA EXEC  
(GILBEAR)

→ Tape must be positioned at the beginning of the appropriate file.

→ **SARLASA HURONA BAND4 A**  
GLOBAL TXLIB CMSLIB FORTMOD2 WBLIB FTIO  
FI 5 TERM  
FI 6 TERM  
FI 15 TERM  
FI 16 TERM  
FI 10 TAP1 ( RECFM FB LRECL 6656 BLOCK 26624  
FI 11 DISK HURONA BAND4 A ( RECFM U BLOCK 6656  
LOAD FLIP ( CLEAR NCMAP START  
EXECUTION BEGINS...  
\*\*\* Enter The Starting Line \*\*\*  
→ 2393  
\*\*\* Enter The Starting Sample \*\*\*  
→ 3560  
\*\*\* Enter The Number Of Lines To Output \*\*\*  
→ 1024  
\*\*\* Enter The Number Of Samples To Output \*\*\*  
→ 1536  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*\* Processing Complete \*\*\*

ORIGINAL PAGE IS  
OF POOR QUALITY

SETUP EXEC

SETUP IASCMD  
(GRABIAS)

→ setup 295 82234  
→ R:ias  
Johnson Space Center  
Interactive Analysis Station (IAS)  
TAPE 380 ON TAPE 380  
!!!  
→ input setup iascmd  
FILEDEF 3 DISK SETUP IASCMD \* (RECFM F LRECL 80 BLKSIZE 80  
INIT  
CURSOR FORM 0  
CURSOR RED  
CURSOR BLINK 0  
IMAGE 0 1 2 3 4 5 6  
ERASE IMAGE  
SIZE 196 162  
IMAGE 1  
WRITE IMAGE MSS295 4  
FILEDEF 4 DISK MSS295 4 \* (RECFM F LRECL 196 BLKSIZE 196  
SIZE 392 324  
IMAGE 2  
WRITE IMAGE TM295 822344  
FILEDEF 4 DISK TM295 822344 \* (RECFM V LRECL 392 BLKSIZE 392  
IMAGE 1  
ZOOM 2  
OS OFF  
PUT 1 6  
IMAGE 2  
ZOOM OFF  
PUT 2 5  
SCREEN 1  
ZCOM OFF  
IMAGE 5  
End of input command file

ORIGINAL PAGE IS  
OF POOR QUALITY

SIZE EXEC  
(GILBEAR)

```
→ size
→ Enter The FN, FT and FM of The File to Be Resized
08932464 1251mag a
*** Enter The Resampling Process To Be Used ***
    (N) ... Nearest Neighbor - (Default)
    (B) ... Bilinear
    (C) ... Cubic Convolution
→ b
→ *** Enter The File Mode Of The Output Data Set ... ( Default = A ) ***
a
EXECUTION BEGINS...
→ *** ENTER THE NUMBER OF LINES TO OUTPUT ***
351
→ *** ENTER THE NUMBER OF SAMPLES TO OUTPUT ***
332
→ *** PARAMETER MENU ***
    DEBUG
    DEBUG
    MENU
    EXIT
→ *** ENTER KEYWORD PARAMETER ... OR RETURN ***
→ *** PROCESSING COMPLETE ***
FILENAME FILETYPE FM  FORMAT  RECS  BLKS  DATE  TIME
08932464 1251MAG  A1  V    392   351   1/17/83  13.24.22
E;
```

Note: NEAREST NEIGHBOR - interpolation to integer pixel and is the fastest and simplest method.

BI-LINEAR - interpolation to fractional pixel and uses nearest 4 pixels.

CUBIC CONVOLUTION - interpolation to fractional pixel and uses nearest 16 pixels. This method is the most pleasing to the eye.

ORIGINAL PAGE IS  
OF POOR QUALITY

TAPCHK EXEC  
(HOCUTT)

→ If tape is used, mount on TAP1.

→ tapchk  
→ IS THE INPUT DATA FROM DISK OR TAPE D/T  
→ t  
O 181  
TAPE 181 ON TAPE 4C3  
FILEDEF 20 TAP1 ( BLOCK 3060 RECFM U PERM  
FILEDEF 10 DISK TAPCHK OUT A ( LRECL 80 BLKSIZE 80 RECFM F PERM  
GLOBAL TYTLIB CMSLIB FORTMOD2 FCRTIBAN PTIO WDBLIB  
LOAD TAPCHK  
START  
EXECUTION BEGINS...  
\*\*\* ENTER THE TAPE NUMBER OR FILE NAME \*\*\*  
→ frh10  
→ R; T=0.86/2.25 12:30:22  
→ t tapchk out

TAPE CHECK PROGRAM RAN ON 3/25/83

FRH10

SEGMENT 893 DATE 8/ 2/82  
TAPE GENERATED ON 1/26/83  
BY THE EODL UNIVERSAL WRITE PROGRAM  
WITH 245 BITS PER WORD IN THE GENERATING COMPUTER  
THE DATA CONSISTS OF 4 CHANNELS  
WITH 1 RECORD FOR EACH DATA SET  
LANDSAT NUMBER 4  
ACTIVE BANDS 1 2 3 4 0 0 0 0  
EACH DATA RECORD CONTAINS 1800 BYTES  
THE TAPE LABEL IS  
"TM893 82214 REGISTERED TO TM893 82246  
TAPE NUMBER RUN ID TM893  
START PIXEL 1 STOP PIXEL 392  
324 DATA RECORDS IN THE FILE  
TAPECHECK FINISHED

ORIGINAL IMAGE ID  
OF POOR QUALITY

TAPCON EXEC  
(GRABIAS)

→ Tape must be mounted on TAP1.

CONVERSION ROUTINE

TAPE NO.  
START FILE  
NO. OF FILES TO PROCESS

→ TAPCON ZTIAS 6250 1 2  
CP REWIND 181  
DEV 181 DOFS NOT EXIST  
+++ R(00040) +++  
TAPMOUNT 6250 TAP1 RO  
IO002 TAPE 6250 HAS BEEN REQUESTED ON UNIT 181 (TAPMCUNT)  
TAPE 181 ATTACHED  
IO003 TAPE READY... EXECUTION CCNTINUING (TAPMOUNT)  
TAPE FSF 0  
EXEC IASCCP ZTIAS  
Enter Input Medium ... Disk or Tape ( D/T )  
TAPE 181 CN TAPE 4C2  
How many segments do you want to skip?  
EXECUTION BEGINS...  
\*\*\* SITE ID IS 7777 \*\*\*

\*\*\* ACQUISITION DATE IS 084 82 \*\*\*

\*\*\* NUMBER OF PIXELS PER LINE IS 512 \*\*\*

CH=	1	BIAS=	32.20	SCALE=	3.70				
CH=	2	BIAS=	30.00	SCALE=	3.10				
CH=	3	BIAS=	16.30	SCALE=	3.00				
CH=	4	BIAS=	12.50	SCALE=	3.00				

FILEDEF	20	DISK	77770841	IASIMAGE	*	(RECFM F	LRECL	512	FLKSIZE	512
FILEDEF	21	DISK	77770842	IASIMAGE	*	(RECFM F	LRECL	512	FLKSIZE	512
FILEDEF	22	DISK	77770843	IASIMAGE	*	(RECFM F	LRECL	512	FLKSIZE	512
FILEDEF	23	DISK	77770844	IASIMAGE	*	(RECFM F	LRECL	512	FLKSIZE	512

\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
7777084 4 512 512  
EXEC IASCCP ZTIAS  
Enter Input Medium ... Disk or Tape ( D/T )  
TAPE 181 CN TAPE 4C2  
How many segments do you want to skip?  
EXECUTION BEGINS...  
\*\*\* SITE ID IS 7777 \*\*\*

\*\*\* ACQUISITION DATE IS 192 82 \*\*\*

\*\*\* NUMBER OF PIXELS PER LINE IS 512 \*\*\*

CH=	1	BIAS=	-176.20	SCALE=	12.70				
CH=	2	BIAS=	-15.00	SCALE=	6.50				
CH=	3	BIAS=	-181.70	SCALE=	5.70				
CH=	4	BIAS=	-118.00	SCALE=	4.10				

FILEDEF	20	DISK	77771921	IASIMAGE	*	(RECFM F	LRECL	512	FLKSIZE	512
FILEDEF	21	DISK	77771922	IASIMAGE	*	(RECFM F	LRECL	512	FLKSIZE	512
FILEDEF	22	DISK	77771923	IASIMAGE	*	(RECFM F	LRECL	512	FLKSIZE	512
FILEDEF	23	DISK	77771924	IASIMAGE	*	(RECFM F	LRECL	512	FLKSIZE	512

\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
7777192 4 512 512  
ALL DONE WITH THIS TAPE...  
CP QUERY TIME  
TIME IS 10:52:37 CST THURSDAY 06/09/83  
CCNNECT= 00:09:09 VIRTCPU= 000:20.59 TOTCPU= 000:47.80  
R:

ORIGINAL FILED  
OF POOR QUALITY

TAPSCAN EXEC  
(GILBEAR)

→ Tape must be mounted on TAP1.

→ tapscan  
\*\*\* Record 1 --- 360 Bytes  
There are 1 Records in the file  
All Are of Length 360 Bytes  
R;  
→ tapscan  
\*\*\* Record 1 --- 3596 Bytes  
There are 2 Records in the file  
All Are of Length 3596 Bytes  
R;  
→ tapscan  
\*\*\* Record 1 --- 1192 Bytes  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
\*\*BLIP\*\*  
There are 8008 Records in the file  
All Are of Length 1192 Bytes  
R;  
→ tapscan  
\*\*\* Record 1 --- 3596 Bytes  
There are 7 Records in the file  
All Are of Length 3596 Bytes  
R;

ORIGINAL PAGE IS  
OF POOR QUALITY

TIEPOINT EXEC  
(GILBEAR)

```

→ tiepoint
→ *** Enter A Unique File Name Identifier ***
→ newtie
→ EXECUTION BEGINS...
→ *** Enter The Number Of Lines In The Reference Image ***
→ 324
→ *** Enter The Number Of Lines In The Registrant Image ***
→ 512
→ *** Enter Reference X ***
→ 27
→ *** Enter Reference Y ***
→ 255
→ --- Enter Registrant X ---
→ 94
→ --- Enter Registrant Y ---
→ 286
→ *** Enter Reference X ***
→ 341
→ *** Enter Reference Y ***
→ 255
→ --- Enter Registrant X ---
→ 403
→ --- Enter Registrant Y ---
→ 290
→ *** Enter Reference X ***
→ 304
→ *** Enter Reference Y ***
→ 18
→ --- Enter Registrant X ---
→ 371
→ --- Enter Registrant Y ---
→ 49
→ *** Enter Reference X ***
→ 71
→ *** Enter Reference Y ***
→ 32
→ --- Enter Registrant X ---
→ 138
→ --- Enter Registrant Y ---
→ 63
→ *** Enter Reference X ***
→
→ FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
→ NEWTIE TIEPTS A1 F 30 5 1/17/83 13.08.25
→ R:

```

ORIGINAL IMAGE IS  
OF POOR QUALITY

TIEREG4 EXEC  
(GILBEAR)

Four tiepoints are needed that are between the center point and the corners, but closer to the corners.

```
→ tiereg4
→ *** Enter The FN, FM And FT Of The Image To Be Registered ***
→ tm893 32294ex1 a
→ *** Enter The FN, FT And FM Of The Registered Image Output ***
→ tm893 reg1
→ *** Enter The FN, FT And FM Of The Tiepoint Data Set ***
→ newtie tiepts a
→ EXECUTION BEGINS...
→ *** TIEPOINT DATA PROCESSED ***
→ *** ENTER THE NUMBER OF LINES TO OUTPUT ***
→ 324
→ *** ENTER THE NUMBER OF SAMPLES TO OUTPUT ***
→ 392
→ *** PROCESSING COMPLETE ***
FILENAME FILETYPE FN FORMAT RECS BLKS DATE TIME
TM893 REG1 A1 V 392 324 1/17/93 13.09.24
R:
```

ORIGINAL PAGE IS  
OF POOR QUALITY

TIEREG5 EXEC  
(GILBEAR)

Approximately 25 evenly distributed tiepoints are needed.

```
→ tiereg5
→ *** Enter The FN, FM And FT Of The Image To Be Regist credi ***
→ tnc000 322400x4
→ *** Enter The FN, FT And FM Of The Regist cred Image Out,ut ***
→ tnc000 322400
→ *** Enter The FN, FT And FM Of The Tiepoint Data Set ***
→ tnc000 322400
EXECUTION BEGINS...

** TIEPOINT DATA PROCESSED ***

→ ** ENTER THE NUMBER OF LINES TO OUTPUT ***
→ 324

→ ** ENTER THE NUMBER OF SAMPLES TO OUTPUT ***
→ 392
*BLIP*
*BLIP*
*BLIP*
*BLIP*
*BLIP*
*BLIP*
*BLIP*

** PROCESSING COMPLETED ***
FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
TNC000 322400 A1 V 392 324 125 2/22/83 7.52.17
R;
```

TIEREG5B EXEC  
(GILBEAR)

Approximately 25 well distributed tiepoints are needed, but more may be needed according to the size.

```

→ TIEREG5B
→ * * * Enter The FN, FM and FT Of The Image To Be Regist ered * * *
→ * * * Enter The FN, FT and FM Of The Regist ered Image Out,ut * * *
→ * * * Enter The FN, FT and FM Of The Tiepoint Data Set * * *
→ EXECUTION BEGINS...

** TIEPOINT DATA PROCESSED ***

→ ** ENTER THE NUMBER OF LINES TO OUTPUT ***
392

→ ** ENTER THE NUMBER OF SAMPLES TO OUTPUT ***
392
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*
*CLIP*

** PROCESSING COMPLETE ***
FILE NAME FILE TYPE FN FOLMAT RECS BLKS DATE TIME
T00006 022404 A1 V 392 324 125 2/22/83 7.32.17
R:

```

TRIBIG EXEC  
(GILBEAR)

ORIGINAL PAGE 10  
OF POOR QUALITY

Because this registration works locally, the user must determine where and the number of corrections or tiepoints that are needed.

```

--> EXEC TRIBIG
--> *** Enter The FN, FM And FT Of The Image To Be Registered ***
--> ns001 chan3 g
--> *** Enter The FN, FT And FM Of The Registered Image Output ***
--> ns001 reg3 a
--> *** Enter The FN, FT And FM Of The Tiepoint Data Set ***
--> newtms tiepts a
EXECUTION BEGINS...
--> *** Enter The Debug Level... 0 = None ***
--> *** Enter The Output Starting Line ***
--> *** Enter The Number Of Lines To Output ***
--> 324
--> *** Enter The Number Of Samples To Output ***
--> 392
+
+
+

```

```

NTri 118
*** TIEPOINT Data Processed ***
+
+
+
+
+
+
+

```

```

*** 50 Lines Processed ***
+
+
+
+

```

```

*** 50 Lines Processed ***
+
+
+
+

```

```

*** 50 Lines Processed ***
+
+
+
+

```

```

*** 50 Lines Processed ***
+
+
+
+

```

```

*** 50 Lines Processed ***
+
+
+
+

```

```

*** Processing Complete ***

```

FILENAME	FILETYPE	FM	FORMAT	RECS	BLKS	DATE	TIME
NS001	REG3	A1	V	392	324	160	5/26/83 16.54

ORIGINAL PAGE IN  
OF POOR QUALITY

TRIREG EXEC  
(GILBEAR)

Because this registration works locally, the user must determine where and how many tiepoints are needed.

```

--> EXEC TRIREG
--> *** Enter The FN, FM And FT Of The Image To Be Registered ***
--> ns001 chan3 g
--> *** Enter The FN, FT And FM Of The Registered Image Output ***
--> ns001 reg3 a
--> *** Enter The FN, FT And FM Of The Tiepoint Data Set ***
--> newtms tiepts a
--> EXECUTION BEGINS...
--> *** Enter The Debug Level ... 0 = None ***
--> *** Enter The Output Starting Line ***
--> *** Enter The Number Of Lines To Output ***
--> 324
--> *** Enter The Number Of Samples To Output ***
--> 392
+
+
+
NTri 118
*** TIEPOINT Data Processed ***
+
+
+
+
+
+
+
*** 50 Lines Processed ***
+
+
+
+
*** 50 Lines Processed ***
+
+
+
+
+
*** 50 Lines Processed ***
+
+
+
+
+
*** 50 Lines Processed ***
+
+
+
+
+
*** 50 Lines Processed ***
+
+
+
+
+
*** Processing Complete ***
FILENAME FILETYPE FM FORMAT RECS BLKS DATE TIME
NS001 REG3 A1 V 392 324 160 5/26/93 16.54

```

ORIGINAL PAGE IS  
OF POOR QUALITY

URITE2 EXEC  
(GILBEAR)  
(HOCUTT)

→ urite2 9657 82234u  
→ Enter the Band  
1  
1 1 324 392 1  
GLOBAL TXTLIB FORTMOD2 CMSLIB WEBLIB FTIO  
FI 5 TERM  
FI 6 TERM  
FI 15 TERM  
FI 16 TERM  
FI 21 DISK TM9657 82234U1 A ( RECFM U BLOCK 3000 PERM  
→ Enter the Band  
2  
1 1 324 392 2  
GLOBAL TXTLIB FORTMOD2 CMSLIB WEBLIB FTIO  
FI 5 TERM  
FI 6 TERM  
FI 15 TERM  
FI 16 TERM  
FI 22 DISK TM9657 82234U2 A ( RECFM U BLOCK 3000 PERM  
→ Enter the Band  
3  
1 1 324 392 3  
GLOBAL TXTLIB FORTMOD2 CMSLIB WEBLIB FTIO  
FI 5 TERM  
FI 6 TERM  
FI 15 TERM  
FI 16 TERM  
FI 23 DISK TM9657 82234U3 A ( RECFM U BLOCK 3000 PERM  
→ Enter the Band  
4  
1 1 324 392 4  
GLOBAL TXTLIB FORTMOD2 CMSLIB WEBLIB FTIO  
FI 5 TERM  
FI 6 TERM  
FI 15 TERM  
FI 16 TERM  
FI 24 DISK TM9657 82234U4 A ( RECFM U BLOCK 3000 PERM  
→ Enter the Band  
5  
1 1 324 392 5  
GLOBAL TXTLIB FORTMOD2 CMSLIB WEBLIB FTIO  
FI 5 TERM  
FI 6 TERM  
FI 15 TERM  
FI 16 TERM  
FI 25 DISK TM9657 82234U5 A ( RECFM U BLOCK 3000 PERM  
→ Enter the Band  
6  
1 1 324 392 6  
GLOBAL TXTLIB FORTMOD2 CMSLIB WEBLIB FTIO  
FI 5 TERM  
FI 6 TERM  
FI 15 TERM  
FI 16 TERM  
FI 26 DISK TM9657 82234U6 A ( RECFM U BLOCK 3000 PERM  
→ Enter the Band  
7  
1 1 324 392 7  
GLOBAL TXTLIB FORTMOD2 CMSLIB WEBLIB FTIO  
FI 5 TERM  
FI 6 TERM  
FI 15 TERM  
FI 16 TERM  
FI 27 DISK TM9657 82234U7 A ( RECFM U BLOCK 3000 PERM

## Enter the Band

Z2 COEFFICIENTS -

## 44

ORIGINAL D. M. IS  
OF POOR QUALITY

WRTAPE EXEC  
(HOCUTT)

→ A scratch tape must be mounted on TAP1.

→ wrtape tm295 82234u  
FILEDEF OUTMOVE TAP1 ( LRECL 3060 BLOCK 3060 RECFM U PERM DEN 1600  
FILEDEF INMOVE DISK TM295 82234U ( LRECL 3060 BLOCK 3060 RECFM U PERM  
MOVEFILE  
R;  
→ wrtape tm9501 82234u  
FILEDEF OUTMOVE TAP1 ( LRECL 3060 BLOCK 3060 RECFM U PERM DEN 1600  
FILEDEF INMOVE DISK TM9501 82234U ( LRECL 3060 BLOCK 3060 RECFM U PERM  
MOVEFILE  
BLIP  
R;  
→ wrtape tm9653 82234u  
FILEDEF OUTMOVE TAP1 ( LRECL 3060 BLOCK 3060 RECFM U PERM DEN 1600  
FILEDEF INMOVE DISK TM9653 82234U ( LRECL 3060 BLOCK 3060 RECFM U PERM  
MOVEFILE  
BLIP  
R;  
→ wrtape tm9654 82234u  
FILEDEF OUTMOVE TAP1 ( LRECL 3060 BLOCK 3060 RECFM U PERM DEN 1600  
FILEDEF INMOVE DISK TM9654 82234U ( LRECL 3060 BLOCK 3060 RECFM U PERM  
MOVEFILE  
R;  
→ wrtape tm9655 82234u  
FILEDEF OUTMOVE TAP1 ( LRECL 3060 BLOCK 3060 RECFM U PERM DEN 1600  
FILEDEF INMOVE DISK TM9655 82234U ( LRECL 3060 BLOCK 3060 RECFM U PERM  
MOVEFILE  
BLIP  
→ wrtape tm9656 82234u  
R;  
FILEDEF OUTMOVE TAP1 ( LRECL 3060 BLOCK 3060 RECFM U PERM DEN 1600  
FILEDEF INMOVE DISK TM9656 82234U ( LRECL 3060 BLOCK 3060 RECFM U PERM  
MOVEFILE  
R;  
→ wrtape tm9657 82234u  
FILEDEF OUTMOVE TAP1 ( LRECL 3060 BLOCK 3060 RECFM U PERM DEN 1600  
FILEDEF INMOVE DISK TM9657 82234U ( LRECL 3060 BLOCK 3060 RECFM U PERM  
MOVEFILE  
BLIP  
R;  
→ wrtape tm9658 82234u  
FILEDEF OUTMOVE TAP1 ( LRECL 3060 BLOCK 3060 RECFM U PERM DEN 1600  
FILEDEF INMOVE DISK TM9658 82234U ( LRECL 3060 BLOCK 3060 RECFM U PERM  
MOVEFILE  
BLIP  
→ R;  
→ tape wtm  
R;